

Instruction manual for ROCAM 4 Android & IOS App and PC-connection




Inhalt:

- How do I establish a connection between an Android device and the ROCAM 4 ? (pages 3-5)
- Which functions are included in the Android app ? (pages 6-8)
- How do I establish a connection between an iPad/iPhone and the ROCAM 4 ? (pages 9-11)
- Which functions are included in the iOS app ? (pages 12-14)
- How do I establish a connection between a PC and the ROCAM 4 ? (pages 15-17)
- Which functions are included in the desktop-version ? (page 18-19)

How do I establish a connection between an Android device and the ROCAM 4 ?

- 1** ■ both Wi-Fi Functions have to be switched on



- 2** ■ connect your Android device with „rocam4_hotspot“



How do I establish a connection between an Android device and the ROCAM 4 ?

- 3** ■ the password is:
„letrocam4in“

- 4** ■ after the connection was
successful you can go on
inside of the app





- 5** ■ you can close the setting menu and go back to the live image

- 6** ■ inside of the app you choose the option „Live Image“ too



Which functions are included in the app ?

- this is your home screen. You can choose between „Live Image“ and your gallery
- after choosing „gallery“ you will see a list of your pictures. To open the pictures, just type them



Which functions are included in the app ?

- now you can choose between the following options:

- after choosing „editing“, the following options will appear:

Microphone (audio-comment)

editing

share



withdraw

rebuild

pen



Colour palette

Save




Which functions are included in the app ?

- choose „pen“ to edit your pictures with the following features
- to share your picture just type the corresponding option





- 1** ■ both Wi-Fi Functions have to be switched on

- 2** ■ connect your iPad/iPhone with „rocam4_hotspot“



- 3** ■ the password is:
„letrocam4in“

- 4** ■ after the connection was
successful you can go on
inside of the app




- 5** ■ you can close the setting menu and go back to the live image

- 6** ■ inside of the app you choose the option „Live Image“ too



Which functions are included in the iOS app ?


- this is your home screen. You can choose between „Live Image“ and your gallery
- after choosing „gallery“ you will see a list of your pictures. To open the pictures, just type them



Which functions are included in the iOS app ?


- now you see your chosen picture. You can choose between 3 options :

- after choosing „editing“, the following options will appear:




Which functions are included in the iOS app ?

- after choosing „share“ the following options will appear:
(depends on your installed programmes)




- 1** ■ the Wi-Fi Function has to be switched on

- 2** ■ connect your PC via the Wi-Fi Function with „rocam4_hotspot“



- 3** ■ the password is:
„letrocam4in“



- 4** ■ the IP-address is needed to
open the desktop-version



- 5** ■ type the IP-adress into the adress bar of your browser to open the desktop version of ROCAM 4 app


- 6** ■ registers from your ROCAM 4 will be automatically adopted

http://192.168.5.1




Which functions are included in the desktop-version ?

- to open the picture just click it



- by right-click these options will appear and you can store the image on your PC



- After a double-click the video will start
- to save the video choose „save target as“

